Lake Name	County	WBIC	Date(s)	AIS sign?	Secchi (ft or m)	Conductivity (ZM tow if ≥99 umhos/cm)
Birch Laxe	Washburn	2113000	7/11/13	Y (N)		Not collected
Data collectors	VALUE NAVO	Lead Monitor phone and	email Start time (~	15 min)	End time (~ 15 min)	Total collector time (hrs x # collectors)
Mauren Ferry.	(A-11/1) (8 " " " " " " " " " " " " " " " " " "	erin. Vernie will and howise	10, 20		5 toD	13 hrs

Look for the following species: Purple loosestrife, Phragmites, flowering rush, Hydrilla, Brazilian waterweed, Eurasian water-milfoil, curly-leaf pondweed, yellow floating heart, zebra mussel, quagga mussel, Chinese mystery snail, banded mystery snail, faucet snail, New Zealand mud snail, didymo, water flea, and any other AIS found.

STEP 1: Record locations of sampling sites (in decimal degrees). Sampling sites include all public boat landings (BL), 5 targeted sites (TS) and the meander survey sites (MS). List AIS found at each site or record none. Collect a sample of any new AIS found. Collect five new invasive plant specimens, 20 Dreissenids, and 30 of each snail species and label with species, collector, date, lake name, WBIC and sampling site.

Site	Latitude	Longitude	Snorkel (Y or N*)	If N snorkel, indicate why	Species, density 1-5 [‡]	: 1/a
BLI	45.65962	-91.55749	Y		BMS:3, UP-3,	cms shells
75	45.46837	91.54173	Y	·	CLP-1	:
<u>TS 2</u>	45,67389	-91.53015	N	blue-green	BMS-1, CUP-3	
J 75 3	45.67463	91.53 924	M	U	CMS-1, CLP-2,	
T54	45.66101	-91.55422	N	blue green	CMS-1, CLP-2, RC-1	
BU		91.54935	7	O	CCD-2, CM s-1	
		÷				

*For lakes/sites not snorkeled, substitute:

Boat landing site - 15 rake throws and 15 D-net samples OR 30 minutes, whichever comes first

Targeted site - 5 rake throws and 5 D-net samples OR 10 minutes, whichever comes first

50 meander sites - 10 rake throws and 10 D-net samples during meander survey between sampling sites for a total of 50 meander survey sites

†If lake/site was not snorkeled, indicate why: stained water, turbid water, blue-green bloom, chemical treatment, other (please describe).

‡ Density Ratings

1 – A few plants or invertebrates

4 – Dense plant, snail or mussel growth in a whole bay or portion of the lake

2 - One or a few plant beds or colonies of invertebrates

5 - Dense plant, snail or mussel growth covering most shallow areas

3 – Many small beds or scattered plants or colonies of invertebrates

Step 2: Collect Waterflea Tows from 3 sites: the deep hole (DH) and 2 other sites in water deeper than 15 feet (if possible). Submit sample and datasheet to Science Services.

Site	Depth sampled	Method (hor, obliq, vert)	Net diameter (30 or 50 cm)	Ethanol added (Y or N)	Samples combined (Y or N)	Sample sent to, date
1	20 ft	oblig	50 cm	γ	\ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \	Gina L. on 8/2/1
2	47. Ft	oblid	50 am		7	
3	40 Fd	0649	50 000	V		<u> </u>

Step 3: Collect Veliger Tows from 3 sites; the deep hole (DH), outlet site (OS), and or downwind site (DS) in water depth of about 4 meters (if possible). Submit sample and Mussel Veliger Tow Monitoring Report form to Science Service.

Site	Depth sampled	Net diameter (30 or 50 cm)	Ethanol added (Y or N)	Samples combined (Y or N)	Sample sent to, date
14)(4m	50 cm	X		GINGL on 8/2/13
DH 2	4 m	50 cm		7	
DH3	Uhr.	EO cm	4	,	V

DH3 4m 50	2 cm	4			V	
Step 4: Were plant voucher specim	ens submitted? Yes No c	ircle) If yes, where	e? (circle) Freckmann He	rbarium, Other		
Step 5: Were snail voucher specime	ens submitted (separate int	o Chinese, banded	I, all others)? (Yes) No (c	ircle) If yes, where? (circle) UW La Cro	osse, or Other
Step 6: Data was entered into SWI	MS on 7/16/13		by Evin Venni	e-Vollva-In		
Step 7: Data was proofed on	9/23/13	by _	Erin Venni	e-Vollvath		
Notes: SWF samples	split into t	wo pot	itles			
ZM veliger s	samples Split	into to	no brilles			

